

Self Explanatory Issues :
Now can be resolved at Customer's end!

SAG Infotech Private Limited

Soft solutions for those can not afford to make errors.

INDEX

LAN Settings to Work on Software at LAN from Server

Preliminary Checks:

| Do's: | Don'ts: |
|--|--|
| <ul style="list-style-type: none">▪ Demo version of desired software must be installed on LAN PC. | <ul style="list-style-type: none">▪ It will not run if you have not taken the Licensed key from us for main Server/PC. |
| <ul style="list-style-type: none">▪ SAG Infotech's Folder must be shared in Server system. [C:>Program Files>SAG Infotech] | |

Structure

LAN SETTING

SERVER PART

CLIENT PART

Sag Infotech folder must be shared

Software must be installed

Before doing local area network.(LAN) connection setting of your software. Keep these point in mind.


Note

- **Your have to be a registered user of the software.**
- **Software must be installed on your node (client) system.**
- **Your system must be shared in your network area.**

Server Part


Go to path (for example) Local disk(C)/Program file/Sag infotech

First share sag infotech folder in network on the server system



Client Part

When you install the software you get icon on desktop , then open the software & click on setting button



After open the software
Just click on the setting
button



Change the path of data
directory . On the LAN
system

Gen SAG Infotech Pvt. Ltd.

Plot No. 495, 1st Floor, Above Bank of Baroda, Raja Park Gali No. 5
Near AC Market, Raja Park, Jaipur - 302 004 (Raj.)
Phone : 0141-4072000 E-Mail : info@saginotech.com
Visit us at : www.saginotech.com

Genius
ver 2.14.2
(2014)

Update Structure Check Database

Settings

Quit

Continue>>

© All Rights Reserved by SAG Infotech Pvt. Ltd.

Checking Registration ...

Gen SAG Infotech Pvt. Ltd.

Settings


| | | |
|---|--------------------------------------|--|
| Database | Genius | <input checked="" type="checkbox"/> Standalone Mode |
| Data Directory | C:\Program Files\SAG Infotech\Genius | |
| Server | localhost | Port 7070 <input checked="" type="checkbox"/> Apply to All |
| Screen Resolution | | |
| Default | 1024 | By 768 DPI 96 |
| <input checked="" type="checkbox"/> Always check for Updates on Startup | | |
| | | Submit Cancel |
| Advance Settings | | |

Settings

Quit


Continue>>

© All Rights Reserved by SAG Infotech Pvt. Ltd.



These are the below mentioned settings:

To be done as example given below to avoid the error at LAN.



| | |
|---------------------|--|
| Database: | Select the Software name e.g. Genius |
| Data Directory: | <ul style="list-style-type: none"> • Syntax: \\<server name>\SAG Infotech<software name> • In given example: \\D1P12\SAG Infotech\Genius |
| Port (SAG service): | 7070 and mark on “Apply to All” |
| Server: | IP Address of server (or) server computer name. |
| Screen Resolution: | Select : Default (1024) By (768) DPI (96) |
| ✓ Mark : | (Always Check for updates on Startup) |
| Unmark Standalone: | Unmark this option on LAN PC. |

Note : How to make such changes is explained in next steps....

Click on **Browse** option of Data Directory, here we have to give path for LAN connectivity.



Now select **My Network Places** and further select the desired **PC/Server** through which LAN is to be connected.

Gen SAG Infotech Pvt. Ltd.

Settings

Database: Genius Standalone Mode

Ph. N Data Directory: C:\Program Files\SAG Infotech\Genius

Server: localhost Port: 7070 Apply to All

Screen Resolution: Default 1024 By 768 DPI 96

Always check for Updates on Startup

Continue>>

© All Rights Reserved by SAG Infotech Pvt. Ltd.

Gen SAG Infotech Pvt. Ltd.

Settings

Database: Genius Standalone Mode

Ph. N Data Directory: \\D1p13\SAG Infotech\Genius

Server: D1p13 Port: 7070 Apply to All

Continue>>

Browse for Folder

C:\



- My Computer
- Local Disk (C:)
- New Volume (D:)
- New Volume (E:)
- d1p7 on 'Sagserver' (*)
- My Network Places**
- Entire Network
- Comm on C1 (d1p1)
- Shared on d1p2
- Shared on d1p4
- shared on d1p6
- Shared on d1p9
- Δkankcha iain

Note: Standalone must be Unmarked from here.

Now Select the path as
PC/Server > SAG Infotech
folder.




Here select the Software folder
you desire to run on LAN and
click **OK** Button.
e.g. Genius



Note : In case of OS is Windows XP, Windows 7, Windows Vista etc.

Select **My Network Places** > **Entire Network** > **Microsoft Windows Network** > **Select the Work Group** > **PC/Server** > **SAG Infotech**.



In above Illustration “**D1P12**” is the Server from where LAN is connected.

This will get the Registration information from Main PC/server and share the software on LAN PC/Server



You are Ready to Work!

Gen SAG Infotech Pvt. Ltd.

Settings

Getting Registration Info

Settings Cancel

Settings Quit Continue>>

© All Rights Reserved by SAG Infotech Pvt. Ltd.

Genius ver 2.12.6.1 (Demo) - LAN - [Welcome]

Genius

12:01:00 PM
30/06/2012

Client Manager

Final Accounts

Income Tax

CMA/EMI

Forms Manager

TDS

Service Tax

Billing

Wealth Tax

Fringe Benefit Tax

AIR

Other Utilities

Help

Press 'F1' for Menu Options


Quit

Check for Update

© All Rights Reserved by SAG Infotech.

Exceptions:

(1) My SQL settings (2) Advance settings



My SQL settings:

This to be checked only if your computer has different version of database from MySQL 4.0
e.g. Any other Higher or lower version.

Note: {Please Call us in such a case}

Advance settings:

{Please refer to Next slide}

ADVANCE SETTINGS (Password: SAG123)

| | |
|----|---|
| U | Marked by default and should also be marked if Offline activation by “Ukey token”. |
| A | Marked by default and should also be marked if Offline activation by “Alladin token”. |
| P | Protocol must be marked by default. |
| H1 | Must be marked by default. |
| H2 | Must be marked by default. |
| H3 | Must be marked by default. |
| H4 | Unmark this option ONLY in following cases: (i) If window of software is not appearing and Logger file is not creating in [C:\\program files\\SAG Infotech]. (ii) If Logger file is created with message: (Automation error in Module:1) |

Thanks for using Our Product and
services!